

Installation instruction

Isadora 3 USB Key Version with USB key license

To be able to save your work in Isadora, the HKU lending and the Blackboxes have USB keys. Below is an instruction:


Download the “Isadora 3 USB key Version” for Windows or MacOS at

1. <https://troikatronix.com/get-it/> under the Downloads heading.

Disclaimer: At the moment licence 4 is out on the Isadora site. HKU needs to transition to this new license. The USB License keys still use version 3.

You can download version 3 on [this](#) page, choose macOS or Windows **USB Key Edition**

Then continue to point 3 on this page.



2. Under the heading “Related Downloads” click on “USB key Version” for Windows or MacOS. Another page appears.

RELATED DOWNLOADS

USB Key drivers, development kits, examples, manuals and more



USB Key Driver (Required if you use a USB Key)	 
Isadora Software Development Kit	 
Isadora Examples	 
Isadora Manual (PDF) English	
Isadora Manual (PDF) Spanish	

3. Scroll to the bottom of the page and click on the correct USB key driver download link for your platform (Windows or MacOS). You will be redirected to the THALES website.

DOWNLOAD THE USB KEY DRIVERS

Important! Only install the latest USB key drivers if you have read all of the information above!

Here are the links to the latest USB key drivers from Thales

[Download the USB Key Drivers for macOS \(Intel / Apple silicon\)](#)

[Download the USB Key Drivers for Windows \(Intel\)](#)

4. Click on the “Sentinel® LDK and Sentinel HASP® Run-time Environment Installer GUI” download link.

Sentinel HASP/LDK Mac OS X Runtime GUI Installation 8.53

KB0018323

Article Details KB0018323

👁 41,303 Views • 📅 Updated: 2022-12-12 • 🗓 Created: 2018-12-10 • ★★★★★

Sentinel® LDK and Sentinel HASP® Run-time Environment Installer for Mac OS X
Refer to the Readme file included in the package for details.

Click here to download file: [DOW0003350](#)

md5hash: 3983e860fabfa0fdedbc17236baf16f3

Filename: Sentinel_Runtime.dmg

File Size: 7.84 MB

5. A pop-up screen appears with the “End User License Agreement”. Scroll down and click “I accept”

End User License Agreement

SENTINEL LDK PRODUCT END USER LICENSE AGREEMENT

IMPORTANT INFORMATION - PLEASE READ THIS AGREEMENT CAREFULLY BEFORE USING THE CONTENTS OF THE PACKAGE AND/OR BEFORE DOWNLOADING OR INSTALLING THE SOFTWARE PRODUCT. ALL ORDERS FOR AND USE OF THE



Scroll down aaaaaaaa!!!!!!!!!! the way

Y. OpenJDK8 is distributed under CDDL License and Gplv2 classpath exception license:
<https://oss.oracle.com/licenses/CDDL+GPL-1.1>


DocID 189 Revision 2110-1

✓ I accept


✗ I do not accept

6. Install the Sentinel USB key for Windows or MacOS.

7. Install "Isadora 3 USB Key Version."
8. Insert the physical Isadora USB Key into the USB port and boot up Isadora.
9. In the Isadora menu bar, go to Help -> Register



10. Copy the code that you receive from a teacher or workshop employee or can find in the lending environment and paste it in the empty registration field.



11. You can now save Isadora patches with the USB key. Have fun!

Note!: If you use a USB (C) adapter, make sure that it stays in place properly. Connection to isadora and the dongle will be disconnected if the adapter moves or becomes loose. Then you cannot save your patch. So save your work regularly.

Revision #9

Created 28 March 2023 13:18:18 by Tjerk

Updated 25 September 2024 10:55:09 by Simone