

Projection Dome

The 360 Dome workspace facility is designed for experimenting with immersive projection and audio. The Projection Dome is only operational during Blackbox IBB opening hours and is used for classes, seminars, and standalone student projects.

- [1. Introduction](#)
 - [Introduction](#)
 - [What is a Projection Dome?](#)
- [2. Prepare your source files](#)
 - [Manual convert 2D video to sphere map](#)
- [3. OBS and Dome](#)
 - [Installing OBS](#)
 - [Adjusting the Canvas Size](#)
- [Other usefull stuff...](#)
- [8 speaker system](#)
- [Connection issues](#)

1. Introduction

Introduction

The HKU Projection Dome

The 360 Dome workspace facility is designed for experimenting with immersive projection and audio. The Projection Dome is only operational during Blackbox IBB opening hours and is used for classes, seminars, and standalone student projects.

Some quick specs about the Projection Dome:


- 4 m diameter
- 4 projectors
- 8 speakers & audio system
- 2 computers, one for media and one with projection dome software called BlendyDomeVJ.

The Dome media computer is used for storing your files and/or running the program you want to use for making or sending your media. This media computer sends the video and sound over a network cable (using NDI protocol, more about that later!) to the second (MAIN DOME) computer where the Projection Dome software called BlendyDomeVJ is running. This makes sure the computer stays clean of student files and its full potential can be used for running the BlendyDomeVJ software. So you can use the other media computer next to it to play your files or you can use your own laptop/pc!

1. Introduction

What is a Projection Dome?

Why would we design in a Dome instead of a normal projection? The spherical shape of the Dome creates an immersive experience for the visitor. Projection Domes have a powerful impact on the senses and can transport you into a whole different world.



2. Prepare your source files

Manuals

2. Prepare your source files

Manual convert 2D video to sphere map

Convert 2D video to sphere map with after effects

<https://youtu.be/fQPeUuhEXdg>



3. OBS and Dome

Example for sending media over NDI using OBS

3. OBS and Dome

Installing OBS

Download OBS from the official website If you're using OBS from your own laptop/pc, make sure to install the NDI Drivers. If your working on the Blackbox Dome Media computer, you don't need to install anything.



[OBS_Reference_Manual.pdf](#)

3. OBS and Dome

Adjusting the Canvas Size

Go to the top menu OBS -> Preferences -> Video Change the Base (Canvas) Resolution to 4000x4000 px Change the Output (Scaled)Resolution to 4000x4000 px Leave the FPS to 60

in case of lag on the line, change resolution to 2000 x 2000 px (canvas & scaled)

equirectangular: 2000x1000

Other usefull stuff...

NDI output vanuit Max/MSP <https://cycling74.com/forums/jit-ndi-externals-for-sending-videoaudio-over-the-network>

Spatial audio tools

Een reeks links naar bruikbare tools voor spatial audio (van blackbox collega Tjerk!):

<https://www.ableton.com/en/packs/surround-panner/> <http://spatialaudio.net/ssr/>
<https://www.envelop.us/software> <https://www.ambisonictoolkit.net>
<https://www.flux.audio/2021/04/14/introducing-spat-revolution-essential-the-power-of-spat-revolution-for-everyone/> <https://freshmania.at/portfolio/spatial-audio-sound-mixer/>
<https://ruipenha.pt/spatium/> <https://sourceforge.net/projects/wfscollider/>

NDI plugin voor OBS

<https://github.com/obs-ndi/obs-ndi/releases>

en vergeet niet ook de NDI runtime te installeren:

<https://ndi.palakis.fr/runtime/ndi-runtime-4.5.1-Windows.exe>

movie convertor voor Ricoh Theta <https://support.theta360.com/uk/download/>

8 speaker system

The Dome setup has an audio setup containing 8 speakers, 1 amplifier, 1 sound interface.

On the MAIN Dome computer the sound interface software can be used to controll the audio system. A configuration template is available File > load > snapshot ...

The Sub speaker is located at monitor output 1. You can find this speaker behind the Dome in the corridor next to Texspace. Turn it on manually, remember to turn it off when finished working ;)

To play audio through this system make sure your audio file is configured the right way. Depending if you want to play audio over 2 or 8 channels. Also if you play your video and audio from the 1st computer make sure the usb cable from the sound interface is plugged in that computer and use the sound interface software on that computer.

Connection issues

Tips for wired connection with Windows laptop:

Turn off WIFI connection

Turn off all firewalls!

Firewall can switch back on after change to ethernet connection, make sure its off.

Change IPv4 settings

IP assignment IPv4: Manual

IPv4 address: same range as Dome mac, change last number (like 192.168. 1.11 or 20 something)

IPv4 subnet prefix length: 16 or 24

IPv4 gateway: 192.168.1.10 (same as Dome mac)

In case you need to fill in subnet mask, make it the same as the Dome mac: 255.255.0.0

Check resolution match!

Lag in image transfer can be caused by resolution & frame rate miss match.

Source Resolution should be 4000 x 4000 (or try 2000 x 2000 if lag stays)

60 fps

Lag can also be caused by Syphon receiver. Turn off Syphon and access your NDI stream directly through Blendydome > Source > NDI > choose source..